

autopuncitems

Kale Ewasiuk (kalekje@gmail.com)

2022-04-16

1 Introduction

This package provides environments `AutoPuncItemize`, `AutoPuncItemize0`, and `AutoPuncItemizeE` (beta) to automatically punctuate the items. By default, it adds the `autopunc (O|E)` options in the `enumitem` environments `itemize`, `enumerate`, and `description`, to wrap the contents in these environments. If you want to skip this (say if you were using the `beamer` class which may be interferred with by `enum item`), pass the `noenumitem` option to this package. You can still use the environments with `beamer`, though. It uses lua pattern matching to modify the environment's contents.

2 Some commands

- `\APomit` Used in an `\item` to signify that that item should not be automatically punctuated, and not be counted. Expands to nothing.
- `\APpass` Used in an `\item` to signify that that item should not be automatically punctuated, and but still counted. Expands to nothing.

```
\setAPeach {}{}{} Set the default, second last, and last punctuation point in that order.  
  \setAPall {} Set all punctuation points the same.  
  \setAPdef {} Set the default punctuation point. ; by default.  
  \setAPseclast {} Set the second last punctuation point. ; and by default.  
  \setAPlast {} Set the second last punctuation point. . by default.
```

- `\enableAPautopassnest` Automatically put an `\APpass` on items that introduce a nested list. Default behaviour.
- `\disableAPautopassnest` Do not automatically put an `\APpass` on items that introduce a nested list.

3 Variants

- autopunc Does not expand the contents of environment. Tutorial on next section shows this.
autopunc0 Expands the contents of environment once. Useful if `\item`'s are in a command
autopuncE Fully expands the contents of environment first. This is in-progress and should not be used.

4 Tutorial

4.1 Basic Use

```
1 \begin{itemize}[autopunc]
2   \item one
3   \item two
4   \item three
5   \item four
6 \end{itemize}
```

- one;
- two;
- three; and
- four.

4.2 Demonstrating Pass

```
1 \begin{itemize}[autopunc]
2   \item one
3   \item two
4   \item three \APpass
5   \item four
6 \end{itemize}
```

- one;
- two;
- three
- four.

```
1 \begin{itemize}[autopunc]
2   \item one
3   \item two
4   \item three \APpass
5   \item four \APpass
6 \end{itemize}
```

- one;
- two;
- three
- four

4.3 Demonstrating Omit

```
1 \begin{itemize}[autopunc]
2   \item one
3   \item two
4   \item three \APomit
5   \item four
6 \end{itemize}
```

- one;
- two; and
- three
- four.

```

1 \begin{itemize}[autopunc]
2   \item one
3   \item two
4   \item three \APomit
5   \item four \APomit
6 \end{itemize}

```

- one; and
- two.
- three
- four

4.4 Nested

You must use `autopunc` on each nested list if you want that sub-list to be automatically punctuated. Note that by default, the item introducing (before) a sub-list will not be automatically punctuated.

```

1 \begin{itemize}[autopunc]
2   \item one
3   \item two
4   \item three:
5     \begin{enumerate}[autopunc]
6       \item alpha:
7         \begin{description}[autopunc]
8           \item[hello] world
9         \end{description}
10      \item beta
11      \item delta
12    \end{enumerate}
13    \item four
14 \end{itemize}

```

- one;
- two;
- three:
 - 1. alpha:
hello world.
 - 2. beta; and
 - 3. delta.
- four.

4.4.1 If you forget to use `APpass`

If you disable auto-pass nested lists, and don't use `\APpass`, here is what happens. Notice the extra “; and” below hello world and beta.

```

1 \disableAPautoPassnest
2 \begin{itemize}[autopunc]
3   \item one
4   \item two
5   \item three
6   \begin{enumerate}[autopunc]
7     \item alpha
8     \begin{description}[autopunc]
9       \item[hello] world
10      \end{description}
11      \item beta
12    \end{enumerate}
13    \item four
14 \end{itemize}

```

- one;
- two;
- three
 - 1. alpha
hello world.
; and
 - 2. beta.
; and
- four.

```

1 \enableAPautopassnest
2 \begin{itemize}[autopunc]
3   \item one
4   \item two
5   \item three
6   \begin{enumerate}
7     \item alpha
8     \begin{description}[autopunc]
9       \item[hello] world
10    \end{description}
11   \item beta
12   \end{enumerate}
13   \item four
14 \end{itemize}

```

- one;
- two;
- three
 - 1. alpha
hello world.
 - 2. beta
- four.

4.5 Expanding list contents

```

1 \def\listexample{
2   \item one
3   \item two
4   \item three
5   \item four
6 }
7 --will work fine (expand once)
8 \begin{itemize}[autopunc0]
9   \listexample
10 \end{itemize}
11
12 --will throw error
13   (author to fix this)
14 \%begin{itemize}[autopuncE]
15 \%   \listexample
16 \%end{itemize}
17
18 --does not give desired result
19   (no items found)
20 \begin{itemize}[autopunc]
21   \listexample
22 \end{itemize}

```

-will work fine (expand once)

- one;
- two;
- three; and
- four.

-will throw error (author to fix this)

-does not give desired result (no items found)

- one
- two
- three
- four

4.6 Using the environment

The normal way to use the environment should be inside the first list, like so.

```
1 \enableAPautoPassnest % default settngs
2 \begin{itemize}
3 \begin{AutoPuncItems}
4     \item one
5     \item two
6     \item three
7     \item four
8 \end{AutoPuncItems}
9 \end{itemize}
```

- one;
- two;
- three; and
- four.

You may want to use the `AutoPuncItems` environment outside a list environment instead, say perhaps if you're using the `beamer`. Note that nested lists are normally not punctuated, and since the first-level list is inside the environment, it's considered nested. If you would like to disable the prevention of auto-punctuating all nested lists, use the `\disableAPprotectnest`. Note that nested lists will cause an error to occur.

```
1 \disableAPprotectnest
2 \begin{AutoPuncItems}
3 \begin{itemize}
4     \item one
5     \item two
6     \item three
7     \item four
8 \end{itemize}
9 \end{AutoPuncItems}
```

- one;
- two;
- three; and
- four