## The **mVersion** package\*

Michael Schmeing michael.schmeing@googlemail.com

March 11, 2013

#### 1 Introduction

The mVersion package is an easy way to keep track of different versions of your document. It provides a counter that can be incremented each time you compile the document. By displaying the counter on each page, (e.g. with the hyperrefpackage) you can see which of two versions is the newer one.

The version number is considered to consist of two parts which are separated by a dot. The first part is a fixed string that can be set by the user with setVersion. The second part is the build number which can be incremented by calling increaseBuild. The command version prints the complete version number, e.g. 0.1.334 with 0.1 being the fixed version number and 334 the build number.

Fixed version number and build number are automatically stored in the file *version.dat* which is created by mVersion. By calling **increaseBuild** in the preamble of your document, you can increase the build number of your document each time you compile.

#### 2 Usage

The mVersion package provides three commands.

This command prints out the version number consisting of the fixed part, followed by a dot and the build number.

Sets the fixed part of the version number

Each time increaseBuild is called, the build number that can be displayed with version is increased by one.

### 3 Implementation

We begin with a small macro **parseline** that reads a line of the form X;Y followed by one space. It then assigns X to **versionnumber** and Y to **buildnumber**. This

version

setBuild increaseBuild

<sup>\*</sup>This document corresponds to mVersion v1.0.1, dated 2013/03/11.

macro helps reading the fixed version number and the build number from the file version.dat. Since LATEX adds an additional space to each line it reads from file, we need this macro.

```
1 \def\parseline#1;#2 %this space is important
2 {
   \def\versionnumber{#1}
3
   \def\buildnumber{#2}
4
5 }
```

#### 3.1Things to do on startup

First, check if version file version.dat exsists.

6 \IfFileExists{version.dat} 7 { }

If not, initialize with version number 0.0 and build number 0 and write the version file to disk. Note that the version file stores the version information in the format X;Y with X being the fixed version number and Y the build number.

```
8 {
9 \newwrite\outfile
10 \immediate\openout\outfile=version.dat
11 \immediate\write\outfile{0.0;0}
12 \immediate\closeout\outfile
13 }
```

After making sure that the version file exists, read version and build number from version file

```
14 \newread\versionfile
15 \openin\versionfile=version.dat
16 \read\versionfile to \versionline
17 \closein\versionfile
```

versionline now contains the version information in the X;Y-format but with an additional space following. Therefore, we let versionline be parsed by pareseline.

18 \expandafter\parseline\versionline

Finally, we initialize the build counter

```
19 \newcounter{buildcounter}
20 \setcounter{buildcounter}{\buildnumber}
```

# **Command definitions**

3.2

\version Get the current version number. 21 \newcommand{\version}{\versionnumber.\thebuildcounter}

setVersion lets you set the fixed version number. First, write the new version \setVersion number and old build number to version file 22 \newcommand{\setVersion}[1]

```
23 {
                24 \newwrite\outfile
                25 \immediate\openout\outfile=version.dat
                26 \immediate\write\outfile{#1;\thebuildcounter}
                27 immediate closeout outfile
                Now re-read version file to re-read version number (not build number)
                28 \newread\versionfile
                29 \openin\versionfile=version.dat
                30 \read\versionfile to \versionline
                31 \expandafter\parseline\versionline
                32 \closein\versionfile
                33 }
\increaseBuild Increase build number by one and save new version and build number to version
                file. By calling increaseBuild in the preamble, the build number is increased
                each time the document is compiled.
                34 \newcommand{\increaseBuild}
                35 {
                Increase build number
                36 \stepcounter{buildcounter}
                Save version and build number to version file
                37 \newwrite\outfile
                38 \immediate\openout\outfile=version.dat
                39 \immediate\write\outfile{\versionnumber; \thebuildcounter}
                40 \verb+\immediate+\closeout+\outfile+
```

```
41 }
```